
Actifio Resiliency Director Deployment Guide on a VMware Server



actifio®

Copyright, Trademarks, and other Legal Matter

Copyright © 2009 - 2020 Actifio, Inc. All rights reserved.

Actifio[®], AnyIT[®], Dedup Async[®], OnVault[®], Enterprise Data-as-a-Service[®], FlashScan[®], AppFlash DEVOPS Platform[®], Copy Data Cloud[®], and VDP[®] are registered trademarks of Actifio, Inc.

Actifio Sky[™], Actifio One[™], and Virtual Data Pipeline[™] are trademarks of Actifio, Inc.

All other brands, product names, goods and/or services mentioned herein are trademarks or property of their respective owners.

Actifio, Inc., is a provider of data protection and availability products. Actifio's technology is used in products sold by the company and products and services sold and offered by its commercial partners. The current list of Actifio patents is available online at: <http://www.actifio.com/patents/>

Actifio believes the information in this publication is accurate as of its publication date. Actifio reserves the right to make changes to information published in this document, including without limitation specifications and product descriptions, at any time and without notice. This document supersedes and replaces all information supplied prior to the publication hereof.

THE INFORMATION IN THIS PUBLICATION IS PROVIDED "AS IS." ACTIFIO, INC. MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND WITH RESPECT TO THE INFORMATION IN THIS PUBLICATION, AND SPECIFICALLY DISCLAIMS IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

This software and the associated documentation are proprietary and confidential to Actifio. Use, copying, and distribution of any Actifio software described in this publication requires an applicable software license. Any unauthorized use or reproduction of this software and the documentation may be subject to civil and/or criminal liability.

Actifio strives to produce quality documentation and welcomes your feedback. Please send comments and suggestions to docs@actifio.com.

Contents

Preface	v
About this Guide	v
Organization of This Guide	v
Actifio Support and Service	v
Chapter 1 - Introduction	1
About Resiliency Director	1
RD Server	1
RD Collector	1
RD Cloud Recovery	1
Chapter 2 - Actifio Resiliency Director Deployment	3
Minimum System Requirements	3
Deploying Resiliency Director OVA	4
Chapter 3 - Configuring the Resiliency Director	5
Configuring Actifio Resiliency Director	5

Preface

About this Guide

The information in this guide is intended for users who are configuring Actifio Resiliency Director on a VMware Server.

Once you have finished configuring Actifio Resiliency Director, consult the Resiliency Director online help. It provides detailed instructions on using Actifio Resiliency Director.

Organization of This Guide

This guide includes the following chapters:

- [Chapter 1, Introduction](#)
- [Chapter 2, Actifio Resiliency Director Deployment.](#)
- [Chapter 3, Configuring the Resiliency Director](#)

Actifio Support and Service

Access these locations for help with your Actifio product suite:

Customer Support Numbers	U.S. Toll-Free Number: 1.855.392.6810 From Anywhere: +1.315.261.7501 Australia: 0011 800-16165656 Germany: 00 800-16165656 New Zealand: 00 800-16165656 UK: 0 800-0155019
Customer Support Email	support@actifio.com
Customer Support Portal	http://support.actifio.com/ When prompted, enter the user name and password provided by your Actifio representative.
General Information	http://www.actifio.com

1 Introduction

About Resiliency Director

Actifio Resiliency Director (RD) is an orchestration product that is used to automate disaster recovery for environments using Actifio appliances for backup and replication to a disaster recovery (DR) site or Cloud. RD coordinates with the Actifio appliances to automate the tasks of recovering VMs, physical servers, and their data in the event of a site-wide outage or disaster at the production site or cloud region. RD allows users to pre-configure the most manual or tedious aspects of the recovery, allowing for one-step recovery of all the in-scope servers and data in a repeatable, reliable, and predictable fashion.

RD Server

The RD Server is the central manager of configuration data for one or more RD Collectors. Data defined on the RD Collector is saved and sent to the RD Server. This enables the RD Server to recover all VMs, vApps, File Systems, and SQL Server Databases in an orchestrated manner in the following circumstances:

- Complete site failure at the production datacenter
- Partial site or application level outage
- DR exercise/test

RD Collector

The Resiliency Director (RD) Collector is a component of RD deployed at each location with source data. The Collector allows the enterprises to discover applications, create groups of applications, and configure details about how the application should be recovered. It then replicates this configuration to one RD Server, typically located at a DR site. Examples of configuration data include:

- Specifying the order of recovery with dependencies
- Specifying which servers/data may be recovered concurrently, vs sequentially
- Specifying new IP addresses to use on recovered servers
- Specifying scripts that should be executed during recovery to facilitate application-level changes that may be required.

RD Cloud Recovery

Resiliency Director (RD) Cloud Recovery is a single instance of Resiliency Director that allows for all configuration and recovery tasks when recovering to a cloud environment. RD Cloud Recovery integrates the components of Resiliency Director Server and Collector, with a focus on recovery into supported cloud environments instead of VMware. RD Cloud Recovery allows the enterprises to recover their VMs, physical servers, System State applications, filesystems, and database applications in the cloud environment of their choice.

2 Actifio Resiliency Director Deployment

This chapter helps you to deploy Resiliency director on a VMware Server.

This chapter contains the following topics:

- [Minimum System Requirements](#) on page 3
- [Deploying Resiliency Director OVA](#) on page 4

Minimum System Requirements

Before deploying the OVA file, ensure that the Resiliency Director server, collector, and cloud recovery meets the following minimum system requirements.

Table 1: Minimum System Requirements

Component	RD Server	RD Collector	RD Cloud Recovery
CPU	8 vCPU	2 vCPU	8 vCPU
Memory (RAM)	16 GB	8 GB	16 GB
Storage	40 GB	40 GB	40 GB
vSphere versions	5.x, 6.0, 6.5, and 6.7	5.x, 6.0, 6.5, and 6.7	5.x, 6.0, 6.5, and 6.7

Deploying Resiliency Director OVA

Actifio Resiliency Director is available in .ova format. You must configure the Actifio Resiliency Director after deploying the ova.

To deploy the Resiliency Director OVA file:

1. Launch the vSphere vCenter client.
2. From **File**, click **Deploy OVF** template.
3. Provide the path of the ActifioRD.ova file and click **Next**.
4. Select the virtual disk type and click **Next**.
5. Provide the details in the VM network properties and select the port group.
6. Confirm the details of the virtual server.
7. Select **Power** on after deployment and click **Finish**. The progress of the OVA deployment appears.
8. Wait for the VM to show its IP address. Use this IP address to configure the Actifio Resiliency Director.

To deploy the Actifio Resiliency Director OVA file using VMware Web Client:

1. Login to the vSphere Web Client <<https://<ip-address>/vsphere-client>>
2. Select **vCenter Server**.
3. Click on **Actions** and choose **Deploy OVF Template** option.
4. Provide the URL or select a local file for the RD virtual appliance and then click **Next**.
URL example: <http://192.168.192.179/files/RD-9.0.2.1234.ova>
5. Provide a name for the RD virtual appliance and select a datacenter or folder, click **Next**.
6. Select a host or cluster or resource pool or vApp, and click **Next**.
7. Review details and click **Next**.
8. Select **Storage** and click **Next**.
9. Select **Networks** and click **Next**.
10. Enter the values for the networking properties and click **Next**.
11. Review the configuration data and click **Finish**.
12. Power on RD appliance after deployment.
13. Wait for the VM to show its IP address. Use this IP address to configure the Actifio Resiliency Director.

3 Configuring the Resiliency Director

When the Actifio Resiliency instance is ready, obtain the instance's Public IP. Once you have the IP you are ready to configure the Actifio Resiliency Director in to the instance.

Configuring Actifio Resiliency Director

To configure the Actifio Resiliency Director:

1. After the VM is deployed, wait until the VM show its IP address.
2. Open a web browser and use the URL `https://<Actifio Resiliency Director IP Address>` to launch the Resiliency Director Configuration page. Use the browser's private, or incognito mode to configure the Actifio Resiliency Director so that the UI is not cached.
3. Change the network parameters to the following values:
 - o Enter/verify the static IP address of the Actifio Resiliency Director in the **Appliance IP** field.
 - o Enter the name of the Actifio Resiliency Director in the **Appliance Name** field.
 - o Enter the DNS Server IP address in the **DNS Server** field.
 - o Enter the **Subnet Mask** and **Gateway** details in the respective fields.
 - o Enter the NTP server IP address in the **NTP Server** field.
 - o Set the administrator password in the **Admin Password** field that you will use while accessing the Resiliency Director. You can change the admin password later using a CLI command.
 - o Select the your time zone from the **Time Zone** drop-down list.

- Select the required Resiliency Director component to be configured from the **RD Type** drop-down list.

The screenshot displays the 'Resiliency Director Configuration' page from Actifio. The page header includes the Actifio logo and the tagline 'Radically Simple'. Below the header, the title 'Resiliency Director Configuration' is followed by a small note: 'IPV6 (Optional) IPv6 Required'. The configuration form contains the following fields and values:

Field	Value
Appliance IP *	172.29.11.115
Appliance Name *	my-rd-server
DNS Server	192.168.192.10,192.168.225.2
Subnet Mask *	255.255.255.0
Gateway *	172.29.11.100
NTP Server	xxx.xxx.xxx.xxx
Admin Password *	*****
TimeZone	(US & Canada) Eastern Time
RD Type	RD Server

A blue 'Save' button is located at the bottom of the form. At the very bottom of the page, there is a copyright notice: '© Actifio Inc. All Rights Reserved'.

4. Click **Save**. The Resiliency Director reboots after setting the configuration.